

HOOF-it® Application Instructions

QUARTER CRACK MIXING INSTRUCTIONS:



Before


After

1. Clean crack with hoof knife or by using a Dremel tool to open the crack.
2. Rasp and sand surrounding hoof surface
3. Mix HOOF-it® II to a stiff putty-like mixture (1 part liquid to 2 parts powder)
4. Fill in the crack(s) using spatula and/or your hands (wet hands in soapy water)
5. Press HOOF-it® II material in to the crack, as needed.
6. Let the repaired patch dry for avg. 2-4 min. depending on outside temperature (hot – fast/ cold – slower dry time).
7. After patch has hardened, rasp and sand area.

(Optional) Apply light protective coat of HOOF-it® II by mixing a small amount. use a brush to paint over the patch and surrounding hoof area to seal.

NOTE: Integrating and applying fiberglass cloth with HOOF-it® II will further strengthen and enhance this repair patch application

MISSING HOOF WALL INSTRUCTIONS:



Before

After

1. Rasp and clean hoof surface.
2. Mix 1 part liquid to 2 parts powder
3. Apply HOOF-it® II mixture into the missing area(s), cracks or the entire hoof. Using wet hands or spatula (gloves optional) to spread HOOF-it II mixture all over the hoof surface.
4. Mold and sculpture HOOF-it® II mixture onto hoof until desired coverage is achieved.

After 2-4 minutes (depending on out-side temperature), nail shoe on.

Let the HOOF-it II material set up before returning horse to pasture or stall.

PAD MIXING INSTRUCTIONS:



1. Thoroughly clean the sole of hoof, remove all debris and insure the hoof is dry.
2. Mix HOOF-it® II powder with liquid in the measuring / mixing cup to a pourable honey like consistency (2 parts powder to 1.5 parts liquid).
3. Pour half the HOOF-it® II mixture onto the hoof sole.
4. Using the applicator stick and wet gloves press the HOOF-it® II resin onto sole, forming a seal where the shoe and sole meet.
5. Now pour the remaining HOOF-it® II mixture to fill the rest of the sole area.
6. Set the hoof down on a clean surface and allow the HOOF-it® II Acrylic pad to cure for approximately 2 minutes.

The HOOF-it II patch or pad can be removed at any time with a hoof pick or by softening the HOOF-it II acrylic with a little dab of acetone if necessary.

NOTE: When the weather is hotter than 75 degrees F, add more liquid to thin the mixture to prevent premature setting up of the acrylic.

